

# MCUXpresso SDK Release Notes Supporting LPC540XX

## 1 Overview

The MCUXpresso Software Development Kit (SDK) is a collection of software enablement for Microcontrollers that includes peripheral drivers, high-level stacks including USB and lwIP, integration with WolfSSL and mbed TLS cryptography libraries, other middleware packages, such as multicore support and FatFs, and integrated RTOS support for FreeRTOS™ OS. In addition to the base enablement, the MCUXpresso SDK is augmented with demo applications and driver example projects, and API documentation to help the customers quickly leverage the support of the MCUXpresso SDK.

For the latest version of this and other MCUXpresso SDK documents, see the MCUXpresso SDK homepage [MCUXpresso-SDK: Software Development Kit](#).

**NOTE**

See the attached Change Logs section at the end of this document to reference the device-specific driver logs, middleware logs, and RTOS log.

## 2 MCUXpresso SDK

### Contents

1	Overview.....	1
2	MCUXpresso SDK.....	1
3	Development Tools.....	2
4	Supported Development Systems.....	2
5	Release Contents.....	2
6	MCUXpresso SDK Release Package... ..	3
7	MISRA Compliance.....	5
8	Known Issues.....	6



## Development Tools

As part of the MCUXpresso software and tools, MCUXpressoSDK is the evolution of Kinetis SDK v2.3.0, includes support for both LPC and i.MX System-on-Chips (SoC). The same drivers, APIs, and middleware are still available with support for Kinetis, LPC, and i.MX silicon. Easily import your SDK into the new MCUXpresso IDE toolchain to have access to all of the available components, examples, and demos for your target silicon. In addition to the MCUXpresso IDE, support for the MCUXpresso Config Tools allows for easy cloning of existing SDK examples and demos, allowing users to easily leverage the existing software examples provided by the SDK for their own projects.

### NOTE

In order to maintain compatibility with legacy FSL code, the filenames and source code in MCUXpresso SDK containing the legacy Freescale prefix 'FSL' has been left as is. The 'FSL' prefix has been redefined as the NXP Foundation Software Library.

## 3 Development Tools

The MCUXpresso SDK was compiled and tested with these development tools:

- IAR Embedded Workbench® for Arm® version 8.20.2
- MDK-Arm Microcontroller Development Kit (Keil)® 5.24
- Makefiles support with GCC revision 6-2017-q2 from Arm Embedded
- MCUXpresso IDE v10.1.1

## 4 Supported Development Systems

This release supports boards and devices listed in this table. Boards and devices in boldface were tested in this release:

**Table 1. Supported MCU devices and development boards**

Development boards	MCU devices
<b>LPCXpresso54018, LPC54018-IoT-Module</b>	LPC54005JET100, LPC54005JBD100, LPC54016JET180, LPC54016JBD208, LPC54016JBD100, LPC54018JBD208, <b>LPC54018JET180</b>

## 5 Release Contents

This table provides an overview of the MCUXpresso SDK release package contents and locations.

**Table 2. Release contents**

Deliverable	Location
Boards	<install_dir>/boards
Demo applications	<install_dir>/boards/<board_name>/demo_apps
USB demo applications	<install_dir>/boards/<board_name>/usb_examples
Driver examples	<install_dir>/boards/<board_name>/driver_examples
Documentation	<install_dir>/docs

*Table continues on the next page...*

**Table 2. Release contents (continued)**

USB Documentation	<install_dir>/docs/usb
Middleware	<install_dir>/middleware
SDMMC card driver	<install_dir>/middleware/sdmmc
USB stack	<install_dir>/middleware/usb
Driver, SoC header files, extension header files and feature header files, utilities	<install_dir>/devices/<device_name>
Cortex Microcontroller Software Interface Standard (CMSIS) ARM Cortex®-M header files, DSP library source	<install_dir>/CMSIS
Peripheral Drivers	<install_dir>/devices/<device_name>/drivers
Utilities such as debug console	<install_dir>/devices/<device_name>/utilities
Tools	<install_dir>/tools

## 6 MCUXpresso SDK Release Package

The MCUXpresso SDK release package contents are aligned with the silicon subfamily it supports. This includes the boards, CMSIS, devices, documentation, middleware, and RTOS support.

### 6.1 Device support

The device folder contains all available software enablement for the specific System-on-Chip (SoC) subfamily. This folder includes clock-specific implementation, device register header file, device register feature header file, CMSIS derived device SVD, and the system configuration source files. Included with the standard SoC support are folders containing peripheral drivers, toolchain support, and a simple debug console.

The device-specific header files provide a direct access to the MCU peripheral registers. The device header file provides an overall SoC memory mapped register definition. In addition to the overall device memory mapped header file, the MCUXpresso SDK also includes the feature header file for each peripheral instantiated on the SoC.

The toolchain folder contains the startup code and linker files for each supported toolchain. The startup code is a CMSIS-compliant startup that efficiently transfers the code execution to the main() function.

#### 6.1.1 Board support

The boards folder provides the board-specific demo applications, driver examples, RTOS, and middleware examples.

#### 6.1.2 Demo applications and other examples

The demo applications demonstrate the usage of the peripheral drivers to achieve a system level solution. Each demo application contains a readme file that describes the operation of the demo and required setup steps.

The driver examples and CMSIS driver examples demonstrate the capabilities of the peripheral drivers. Each example implements a common use case to help demonstrate the driver functionality.

The middleware folders each contain examples demonstrating the use of the included source.

## 6.2 Middleware

### 6.2.1 USB stack

See the *MCUXpresso SDK USB Stack User's Guide* (document USBSUG) for more information.

#### 6.2.1.1 Peripheral devices tested with the USB Host stack

This table provides a list of USB devices tested with the USB Host stack.

**Table 3. Peripheral devices**

Device type	Device
USB HUB	BELKIN F5U233
	BELKIN F5U304
	BELKIN F5U307
	BELKIN F4U040
	UNITEK Y-2151
	Z-TEK ZK032A
	HYUNDAI HY-HB608
USB flash drive	ADATA C008 32 GB
	ADATA S102 8 G
	ADATA S102 16 G
	Verbatim STORE N GO USB Device 8 G
	Kingston DataTraveler DT101 G2
	SanDisk Cruzer Blade 8 GB
	Unisplendour 1 G
	Imation 2 GB
	V-mux 2 GB
	Sanmina-SCI 128 M
	Corporate Express 1 G
	TOSHIBA THUHYBS-008G 8 G
	Transcend JF700 8 G
	Netac U903 16 G
	SSK SFD205 8 GB
	Rex 4 GB
	SAMSUNG USB3.0 16GB

*Table continues on the next page...*

**Table 3. Peripheral devices (continued)**

USB card reader/adapter	SSK TF adapter Kawau Multi Card Reader Kawau TF adapter Kawau SDHC card
USB Mouse	DELL MS111-P DELL M066U0A DELL MUAVDEL8 TARGUS AMU76AP DELL MD56U0 DELL MS111-T RAPOO M110
USB Keyboard	DELL SK8135 DELL SK8115

## 6.2.2 CMSIS

The MCUXpresso SDK is shipped with the standard CMSIS development pack, including the prebuilt libraries.

## 6.2.3 emWin

The MCUXpresso SDK is pre-integrated with the SEGGER emWin GUIBuilder.

# 7 MISRA Compliance

All MCUXpresso SDK drivers and USB stack comply to MISRA 2004 rules with the following exceptions.

## Known Issues

Exception Rules	Description
1.1	All code shall conform to ISO 9899:1990 Programming languages - C, amended and corrected by ISO/IEC 9899/COR1:1995, ISO/IEC 9899/AMD1:1995, and ISO/IEC
2.4	Sections of code should not be commented out.
5.1	Identifiers (internal and external) shall not rely on the significance of more than 31 characters.
6.3	typedefs that indicate size and signedness should be used in place of the basic types.
6.4	Bitfields shall only be defined to be of type unsigned int or signed int.
8.1	Functions shall have prototype declarations and the prototype shall be visible at both the function definition and call.
8.5	There shall be no definitions of objects or functions in a header file.
8.1	All declarations and definitions of objects or functions at file scope shall have internal linkage unless external linkage is required.
8.12	When an array is declared with external linkage, its size shall be stated explicitly or defined implicitly by initialization.
	The value of an expression of integer type shall not be implicitly converted to a different underlying type if:
	a. it is not a conversion to a wider integer type of the same signedness, or
	b. the expression is complex, or
	c. the expression is not constant and is a function argument, or
10.1	d. the expression is not constant and is a return expression.
10.3	The value of a complex expression of integer type shall only be cast to a type that is not wider and of the same signedness as the underlying type of the expression.
11.3	A cast should not be performed between a pointer type and an integral type.
11.4	A cast should not be performed between a pointer to object type and a different pointer to object type.
11.5	A cast shall not be performed that removes any const or volatile qualification from the type addressed by a pointer.
12.2	The value of an expression shall be the same under any order of evaluation that the standard permits.
12.4	The right-hand operand of a logical && or    operator shall not contain side effects.
12.6	The operands of logical operators (&&,   , and !) should be effectively boolean. Expressions that are effectively boolean should not be used as operands to operators other than (&&,   , !, =, ==, !=, and ?-).
12.13	The increment (++) and decrement (--) operators should not be mixed with other operators in an expression.
14.3	Before preprocessing, a null statement shall only occur on a line by itself; it may be followed by a comment, provided that the first character following the null statement is a whitespace character.
14.5	The continue statement shall not be used.
14.7	A function shall have a single point of exit at the end of the function.
16.1	Functions shall not be defined with a variable number of arguments.
17.4	Array indexing shall be the only allowed form of pointer arithmetic.
18.4	Unions shall not be used.
19.1	#include statements in a file should only be preceded by other preprocessor directives or comments.
19.1	In the definition of a function-like macro, each instance of a parameter shall be enclosed in parentheses unless it is used as the operand of # or ##.
20.4	Dynamic heap memory allocation shall not be used.
20.9	The input/output library <stdio.h> shall not be used in production code.

Figure 1. MISRA exceptions

## 8 Known Issues

### 8.1 Maximum file path length in Windows® 7 Operating System

Windows 7 operating system imposes a 260 character maximum length for file paths. When installing the MCUXpresso SDK, place it in a directory close to the root to prevent file paths from exceeding the maximum character length specified by the Windows operating system. The recommended location is the C:\nxp folder.

### 8.2 USB HUB Power supply

The external power supply of the USB HUB must be provided before it can be used. The development board power is not enough to supply multi-level USB HUBs and connected devices. Therefore, the external USB HUB that is connected to the development board should have its own power supply.

### 8.3 USBFS controller issue

Because of the USBFS controller design issues, the USB host suspend/resume demos (usb\_suspend\_resume\_host\_hid\_mouse) of the full speed controller do not support the low speed device directly.

## 8.4 SDIF issue

If the user uses this module to access the SD card/MMC card, `sd_data[4-7]` must be enabled and configured as input and pull up. It is better to use P4\_17 to P5\_10, otherwise 4-bit mode does not work.

## 8.5 USB High-Speed Interrupt Endpoint issue

If the user wants to use a high-speed interrupt endpoint, the maximum packet size should be 512 bytes.

## 8.6 Debug SRAM target with J-Link on MCUXpresso IDE issue

If using the J-Link to Debug SRAM target on the IDE, when clicking the Restart button, the debug fails. The issue is caused because the integrity of the SRAM image cannot be guaranteed after it has been executed, and the MCUXpresso IDE does not reload the code before restarting.

Plain load images (images loaded from external SPI flash to SRAMX by the ROM bootloader then executed) cannot be debugged using MCUXpresso version 10.1.1. Code should be developed using the SRAM debug method, then the code programmed into flash once debugging is completed. See *Getting Started with MCUXpresso SDK for LPC540xx* (document MCUXSDKLPC540XXGSUG), included with this release.

**How to Reach Us:****Home Page:**[nxp.com](http://nxp.com)**Web Support:**[nxp.com/support](http://nxp.com/support)

Information in this document is provided solely to enable system and software implementers to use NXP products. There are no express or implied copyright licenses granted hereunder to design or fabricate any integrated circuits based on the information in this document. NXP reserves the right to make changes without further notice to any products herein.

NXP makes no warranty, representation, or guarantee regarding the suitability of its products for any particular purpose, nor does NXP assume any liability arising out of the application or use of any product or circuit, and specifically disclaims any and all liability, including without limitation consequential or incidental damages. "Typical" parameters that may be provided in NXP data sheets and/or specifications can and do vary in different applications, and actual performance may vary over time. All operating parameters, including "typicals," must be validated for each customer application by customer's technical experts. NXP does not convey any license under its patent rights nor the rights of others. NXP sells products pursuant to standard terms and conditions of sale, which can be found at the following address: [nxp.com/SalesTermsandConditions](http://nxp.com/SalesTermsandConditions).

NXP, the NXP logo, NXP SECURE CONNECTIONS FOR A SMARTER WORLD, COOLFLUX, EMBRACE, GREENCHIP, HITAG, I2C BUS, ICODE, JCOP, LIFE VIBES, MIFARE, MIFARE CLASSIC, MIFARE DESFire, MIFARE PLUS, MIFARE FLEX, MANTIS, MIFARE ULTRALIGHT, MIFARE4MOBILE, MIGLO, NTAG, ROADLINK, SMARTLX, SMARTMX, STARPLUG, TOPFET, TRENCHMOS, UCODE, Freescale, the Freescale logo, Altivec, C-5, CodeTest, CodeWarrior, ColdFire, ColdFire+, C-Ware, the Energy Efficient Solutions logo, Kinetis, Layerscape, MagniV, mobileGT, PEG, PowerQUICC, Processor Expert, QorIQ, QorIQ Qonverge, Ready Play, SafeAssure, the SafeAssure logo, StarCore, Symphony, VortiQa, Vybrid, Airfast, BeeKit, BeeStack, CoreNet, Flexis, MXC, Platform in a Package, QUICC Engine, SMARTMOS, Tower, TurboLink, and UMEMS are trademarks of NXP B.V. All other product or service names are the property of their respective owners. ARM, AMBA, ARM Powered, Artisan, Cortex, Jazelle, Keil, SecurCore, Thumb, TrustZone, and  $\mu$ Vision are registered trademarks of ARM Limited (or its subsidiaries) in the EU and/or elsewhere. ARM7, ARM9, ARM11, big.LITTLE, CoreLink, CoreSight, DesignStart, Mali, mbed, NEON, POP, Sensinode, Socrates, ULINK and Versatile are trademarks of ARM Limited (or its subsidiaries) in the EU and/or elsewhere. All rights reserved. Oracle and Java are registered trademarks of Oracle and/or its affiliates. The Power Architecture and Power.org word marks and the Power and Power.org logos and related marks are trademarks and service marks licensed by Power.org.

© 2018 NXP B.V.

Document Number MCUXSDKLPC540XXRN  
Revision 0, 01/2018

